

Instructions for Installing TReK 4.0.0 on Windows

Installing TReK Using .exe File:

Copy the .exe install file to the computer. Double click the file and follow the instructions on the dialogs.

Installing TReK From the Command Prompt Using .msi File:

Bring up the command prompt. Type the following command to install to the default location in quiet mode so that no dialogs pop up:

Note: The .msi file name will change on each release. Also, you can use “/passive” instead of “/quiet”.

```
C:\Users\user> msixec /i TReKRelease.msi /quiet ACCEPTEULA=1
```

If you would like the TReK software to install somewhere other than the default location you can add the “/INTALLDIR=” option specifying the directory for where you would like it installed. For instance, the following command will install the software to the “D:\TReK 0.2.0” path.

```
C:\Users\user> msixec /i TReKRelease.msi /passive ACCEPTEULA=1  
/INTALLDIR="D:\TReK 0.2.0"
```

Uninstalling TReK From the Command Prompt Using .msi File:

To uninstall the software from the command line using the .msi file name that you installed it with use the following command:

```
C:\Users\user> msixec /x TReKRelease.msi /passive
```