

# Instructions for Installing TReK 5.0.1 on Microsoft Windows

## ***Installing Required Third Party Libraries:***

TReK requires several third party libraries. Most of these are already provided as part of the TReK Windows install. One that is not included is the Interplanetary Overlay Network (ION) version 3.3.1b. You can get the Windows install for ION 3.3.1b from the TReK website.

## ***Installing TReK Using .exe File:***

Copy the .exe install file to the computer. Double click the file and follow the instructions on the dialogs.

## ***Installing TReK From the Command Prompt Using .msi File:***

Bring up the command prompt. Type the following command to install to the default location in quiet mode so that no dialogs pop up:

*Note: The .msi file name will change on each release. Also, you can use “/passive” instead of “/quiet”.*

```
C:\Users\user> msexec /i TReKRelease.msi /quiet ACCEPTEULA=1
```

If you would like the TReK software to install somewhere other than the default location you can add the “INSTALLDIR=” option specifying the directory for where you would like it installed. For instance, the following command will install the software to the “D:\TReK 5.0.1” path.

```
C:\Users\user> msexec /i TReKRelease.msi /passive ACCEPTEULA=1  
INSTALLDIR="D:\TReK 5.0.1"
```

## ***Uninstalling TReK From the Command Prompt Using .msi File:***

To uninstall the software from the command line using the .msi file name that you installed it with use the following command:

```
C:\Users\user> msexec /x TReKRelease.msi /passive
```