

# Instructions for Installing TReK 5.3.2 on Microsoft Windows

## ***Third Party Libraries:***

TReK 5.3.2 comes with all third party software needed to run including ION 3.6.2. Read the next two paragraphs about previous versions of TReK.

Beginning with TReK 5.1.1 all third party software is included with the TReK install. Previous versions of TReK required that third party software be installed separately. Prior to installing TReK 0.13.0 it is recommended that you uninstall all previous versions of TReK 4.x and 5.x as well as uninstall all third party software provided for TReK. *Note: It is safe to leave any version of TReK 3.x on your computer.*

For Windows, you can use the Add/Remove Programs feature to uninstall any version of TReK and also ION 3.3.1b which was used for TReK 5.0.1 and earlier. If you have TReK 5.1.0 installed, ION was provided as a separate installer. The uninstaller for ION-3.6.1 is available in the ION directory on your computer. The default location for the install was c:/ION.

If you have any questions about or issues with the uninstall, please contact the TReK Help Desk at [trek.help@nasa.gov](mailto:trek.help@nasa.gov).

## ***Installing TReK Using .exe File:***

Copy the .exe install file to the computer. Double click the file and follow the instructions on the dialogs.

## ***Installing TReK From the Command Prompt Using .msi File:***

Bring up the command prompt. Type the following command to install to the default location in quiet mode so that no dialogs pop up:

*Note: The .msi file name will change on each release. Also, you can use "/passive" instead of "/quiet".*

```
C:\Users\user> msiexec /i TReKRelease.msi /quiet ACCEPTEULA=1
```

If you would like the TReK software to install somewhere other than the default location you can add the "INSTALLDIR=" option specifying the directory for where you would like it installed. For instance, the following command will install the software to the "D:\TReK 5.3.2" path.

```
C:\Users\user> msiexec /i TReKRelease.msi /passive ACCEPTEULA=1  
INSTALLDIR="D:\TReK 5.3.2"
```

## ***Uninstalling TReK From the Command Prompt Using .msi File:***

To uninstall the software from the command line using the .msi file name that you installed it with use the following command:

```
C:\Users\user> msiexec /x TReKRelease.msi /passive
```