

Instructions for Installing TReK 5.4.0 on Microsoft Windows

Third Party Libraries:

TReK 5.4.0 comes with all third party software needed to run including ION 3.6.2.

At TReK 5.1.1, all third party software has been included with the install. Previous versions required that third party software be installed separately. Prior to 5.3.3 it is recommended that you uninstall all previous versions of TReK 4.x and 5.x as well as uninstall all third party software provided for TReK. *Note: It is safe to leave any version of TReK 3.x on your computer.*

For Windows, you can use the Add/Remove Programs feature to uninstall any version of TReK and also ION 3.3.1b which was used for TReK 5.0.1 and earlier. If you have TReK 5.1.0 installed, ION was provided as a separate installer. The uninstaller for ION-3.6.1 is available in the ION directory on your computer. The default location for the install was c:/ION.

If you have any questions about or issues with the uninstall, please contact the TReK Help Desk at trek.help@nasa.gov.

Installing TReK From the Command Prompt Using .msi File:

To install TReK, run the following command as administrator, replacing `TReKRelease.msi` with the actual MSI filename:

```
msiexec /i TReKRelease.msi
```

For silent installation, use `/qn` or `/passive`:

```
msiexec /i TReKRelease.msi /qn
```

To specify an installation directory for silent installations:

```
C:\Users\user> msiexec /i TReKRelease.msi /qn INSTALLDIR="D:\TReK 5.4.0"
```

Uninstalling TReK From the Command Prompt Using .msi File:

Use this command, replacing `TReKRelease.msi` with the original MSI filename:

```
C:\Users\user> msiexec /x TReKRelease.msi /qn
```